

# IUAdmin v1.5

## Configuration

### Configuring IUAdmin

IUAdmin configuration is done with IUAdmin itself. You reach the configuration page by attaching to the IUAdmin Advanced page with your browser and clicking on "IUAdmin Administration". This page will guide you through the various configuration options available to you along with complete documentation on each option.

The configuration options are:

### Configuration Item Description

**Connected Users** -List all users currently using IUAdmin along with their IP address and other session details.

**User Index** -Configure where in your tree the user objects are.

**User Self-Service** -Configure parameters related to web password change, self-service password reset, and other self-service tasks

**All Users Help Desk** -Define users, or groups of users that have HelpDesk authority over all users in the index. Also define the rights that the HelpDesk has, such as the ability reset passwords or change home directory quotas.

**Location HelpDesk**- Define users or groups of users that have HelpDesk authority over all users in a given Location. This is based on the Location attribute of the target user.

**Department HelpDesk**- Define users or groups of users that have HelpDesk authority over all users in a given Department. This is based on the Department attribute of the target user.

**Program Security**- Configure various parameters related to the security behind IUAdmin.

**E-Mail**- Configure various parameters related to the E-Mail subsystem in IUAdmin and how it interacts with your existing SMTP mail server.

**AuditLogin**- IUAdmin can interact with the forthcoming Version 4 of AuditLogin to display real-time server connection information for any user in the tree to any server in the tree, regardless of whether the given user is using IUAdmin or not. This section sets the parameters that control that interaction.

**Resource Management**- Configure various aspects of the IUAdmin Resource Portal.

**Appearance**- Customize the appearance, layout, and content of IUAdmin. See example doc from this section below.

**Troubleshooting**- Information about troubleshooting IUAdmin along with links to various related information on the Internet.

One of the options is "**Appearance**" where you can customize the IUAdmin interface. The following is the documentation that is shown on that page and is

provided here as an example of the type of documentation that you can expect in the product.

---

## **IUAdmin Interface Customization**

### **Preface**

The architecture of IUAdmin supports customization of both the content and cosmetic attributes of the user interface. This document describes the options available to you.

### **Layout Options**

The sample page below shows the various page layout and customization options available to you. See the table below for detailed information.

### **Option Description Details**

#### **Option Description Detail**

- 1 **Introductory Page** The main window of the IUAdmin home page is defined by the HTML in WELCOME.HTM in the \IUADMIN directory. You can replace the information there with your own information, including links and graphics.
- 2 **IUAdmin Graphic** This graphic is LOGO.JPG in the \IUADMIN directory. You should replace this graphic with one that represents your organization. In a default configuration, this graphic should be approximately 150 pixels wide. However, it will be resized in the browser to be the defined width of the menu. See "Column Customization" section below for more information.
- 3 **Footer** The footer information is displayed at the bottom of every page. It is defined by the HTML in FOOTER.HTM in the \IUADMIN directory. You can replace the information there with your own information, including links and graphics.
- 4 **Header Background Graphic** The graphic behind the header is MENTOP.JPG in the \IUADMIN directory. You can replace this graphic with one of your own.
- 5 **Menu Background Graphic** The graphic behind the header is DEFTOP.JPG in the \IUADMIN directory. You can replace this graphic with one of your own. . In a default configuration, this graphic should be approximately 150 pixels wide, but is customizable. See "Column Customization" section below for more information.
- 6 **Main Window Background Color** This is the color of the background in the main IUAdmin Window. The default is Grey. You can change this parameter in the "Appearance" section of the IUAdmin parameters.
- 7 **Main Window Font Color** This is the color of the font in the main IUAdmin Window. The default is BLACK. You can change this parameter in the "Appearance" section of the IUAdmin parameters.

### **Menu Customization**

You have the option of adding your own items to the IUAdmin menus by editing

the ENDUSER.HTM and/or ADVANCED.HTM files in the /IUADMIN directory. Once you start IUAdmin, see the "Program Security" section of IUAdmin configuration for more information on the "EndUser" and "Advanced" user designations.

### **Column Customization**

In the default configuration, the page is split from left to right so that the menu column is 150 pixels wide and the remainder of the browser window is devoted to displaying data. This is a configurable parameter however. If you modify the background menu graphic (defined above as layout option #5), you may want to change this parameter to match the width of the background graphic. If not, the Netscape and Microsoft browsers will pad with white space if the graphic is less than 150 pixels and chop the graphic off if it is more than 150 pixels. You can change this parameter in the "Appearance" section of the IUAdmin parameters.